mount and lsblk Disks and mounts

Block device /dev/sdb1 —mkfs→ **Filesystem** UUID, label —mount→ **Mount point** /mnt/data —umount→ **Detached** safe to unplug

CONCEPTS

Mount points are just directories: mounting hides whatever was in them until you unmount.

Use UUID= in fstab: /dev/sdX names can change between boots.

DISCOVER

`lsblk`
Tree of block devices

`lsblk -f`
Add filesystem, label, UUID, mountpoint

`sudo blkid`
List UUID, label and type of devices

`findmnt`
Tree of mounted filesystems

`findmnt <dir>`
Which filesystem backs this mount point

`findmnt -T <path>`
Mount holding any path

MOUNT AND UNMOUNT

`sudo mount <device> <dir>`
Mount, type auto-detected

MOUNT AND UNMOUNT (cont.)

`sudo mount -t <type> <device> <dir>`
Force the filesystem type

`sudo mount -o <opts> <device> <dir>`
Mount with comma-separated options

`sudo mount -r <device> <dir>`
Mount read-only

`sudo mount UUID=<uuid> <dir>`
Mount by UUID

`sudo mount -a`
Mount all fstab entries not yet mounted

`sudo mount -o loop <file.iso> <dir>`
Mount an image file

`sudo umount <dir>`
Unmount by mount point

`sudo umount <device>`
Unmount by device

`sudo umount -l <dir>`
Lazy: detach now, clean up later

"target is busy": find the culprit with lsof +f -- <dir> or fuser -vm <dir>, or cd out of it.

BIND AND REMOUNT

`sudo mount --bind <dir> <other>`
Make a directory visible at a second path

`sudo mount --rbind <dir> <other>`
Bind including submounts

`sudo mount -o remount,ro <dir>`
Switch a live mount to read-only

`sudo mount -o remount,rw <dir>`
Switch a live mount to read-write

`sudo mount -o remount,noatime <dir>`
Change options without unmounting

FSTAB AND OPTIONS

fstab fields (/etc/fstab)

#	Field	Example
1	device or UUID=	UUID=1a2b-3c4d
2	mount point	/data
3	filesystem type	ext4
4	options	defaults,noatime
5	dump (legacy)	0
6	fsck order	2

FSTAB AND OPTIONS (cont.)

A typical fstab line

```
# device        dir    type
options           dump pass
UUID=<uuid>     /data  ext4
defaults,noatime  0    2
```

Common options

Option	Effect
`defaults`	rw,suid,dev,exec,auto,nouser,async
`ro / rw`	read-only / read-write
`noexec`	forbid running binaries
`nosuid`	ignore setuid bits
`nodev`	ignore device files
`noatime`	skip access-time writes
`nofail`	do not fail boot if absent
`noauto`	skip on mount -a and boot
`user`	non-root users may mount
`x-systemd.automount`	mount on first access

FSTAB AND OPTIONS (cont.)

`findmnt --verify`
Lint fstab before rebooting

`sudo systemctl daemon-reload`
Make systemd re-read fstab

Test an fstab edit with `mount -a` before rebooting; a bad entry can drop boot into emergency mode.

Put nofail on removable or network disks so a missing one cannot block boot.

RECIPES

Mount a new USB disk

```
lsblk -f
sudo mkdir -p /mnt/usb
sudo mount /dev/sdb1 /mnt/usb
# when done
sudo umount /mnt/usb
```

Persist a disk across reboots

```
lsblk -f
# note the UUID
sudo mkdir -p /data
echo 'UUID=<uuid> /data ext4 defaults,nofail 0 2' | sudo tee -a /etc/fstab
findmnt --verify && sudo mount -a
```