Uvicorn ASGI web server

CONCEPTS

main:app means module:variable. Uvicorn serves ASGI apps (FastAPI, Starlette, Django ASGI) and listens on 127.0.0.1:8000 by default.

Client browser
↓ HTTPS
nginx TLS, static
↓ unix socket
Uvicorn HTTP and ASGI
↓ ASGI
Your app FastAPI etc.

Defaults to 127.0.0.1, so a container needs --host 0.0.0.0 or it is unreachable from outside.

--reload and --workers cannot be combined. Use --reload for development only, workers or Gunicorn for production.

RUN

`uvicorn` *`<module>:<app>`*
Serve an ASGI app

`uvicorn --factory` *`<module>:<func>`*
Treat app as a factory

`uvicorn` *`<module>:<app>`* **`--reload`**
Auto-restart on file change

`uvicorn` *`<module>:<app>`* **`--workers`** *`<n>`*
Run n worker processes

`uvicorn --version`
Print the version

`uvicorn --help`
List all options

BINDING

`--host` *`<addr>`*
Bind address (default 127.0.0.1)

`--port` *`<n>`*
Bind port (default 8000)

BINDING (cont.)

`--uds` *`<path>`*
Bind a Unix socket

RELOAD

`--reload`
Watch files and restart

`--reload-dir` *`<dir>`*
Watch this directory only

WORKERS AND LIMITS

`--workers` *`<n>`*
Number of worker processes

`--timeout-keep-alive` *`<sec>`*
Idle keep-alive timeout (default 5)

`kill -HUP` *`<pid>`*
Gracefully restart workers

PROTOCOLS

`--http` *`<impl>`*
h11 or httptools

LOGGING

`--log-level` *`<level>`*
critical, error, warning, info, debug, trace

`--no-access-log`
Silence request lines

HTTPS AND PROXIES

`--ssl-keyfile` *`<key>`* **`--ssl-certfile`** *`<crt>`*
Serve HTTPS directly

`--proxy-headers`
Read X-Forwarded-For and -Proto

`--forwarded-allow-ips` *`<ips>`*
Trusted proxy IPs or sockets

GUNICORN AND CODE

Gunicorn with Uvicorn workers

```
pip install uvicorn-worker
gunicorn main:app -w 4 -k
uvicorn_worker.UvicornWorker
```