iftop Live bandwidth by host

CONCEPTS

iftop needs raw packet capture: run it with sudo and name the interface with -i, or it picks the first one.

iftop -nNP who talks
Sort 1-3 2s / 10s / 40s
Filter l or -f
Capture tcpdump
Reading a busy link

The three columns are average rates over 2, 10 and 40 seconds; the bottom bar shows cumulative, peak and rate totals.

DISPLAY

r
Toggle hostname resolution

p
Toggle port display

S
Toggle source port

D
Toggle destination port

t
Cycle line display modes

P
Pause the display

o
Freeze current ordering

j / **k**
Scroll the host list

SORTING AND GROUPING

s
Aggregate by source host

d
Aggregate by destination host

SORTING AND GROUPING (cont.)

1 / **2** / **3**
Sort by column 1, 2 or 3

<
Sort by source name

>
Sort by destination name

l
Filter hostnames by regex

f
Edit the capture filter live

h / **?**
Show built-in help

COMMAND LINE

iftop › **-i** › *<if>*
Listen on an interface

iftop › **-n**
No hostname lookups

iftop › **-N**
No port-to-service names

iftop › **-P**
Show ports

iftop › **-B**
Rates in bytes, not bits

iftop › **-f** › **"<filter>"**
Capture filter (pcap syntax)

iftop › **-F** › *<net/mask>*
Measure direction relative to a network

iftop › **-p**
Promiscuous mode

iftop › **-b**
No bar graphs

iftop › **-m** › *<limit>*
Bar scale limit (K, M, G)

iftop › **-t**
Plain text output, no ncurses