iperf3 Network throughput tester

CONCEPTS

iperf3 needs a server at one end and a client at the other; it measures the path between them, not either machine alone. Test only networks and hosts you are authorised to use.

Server iperf3 -s, port 5201
↓ control
Client iperf3 -c host
↓ data streams
Interval reports every 1 s
↓ summary
Sender / receiver final totals

Default direction is client to server. -R reverses it, so the client receives; --bidir does both at once. Open TCP and UDP port 5201 in any firewall in between.

SERVER

iperf3 -s
Listen for tests (port 5201)

iperf3 -s -p *<port>*
Listen on another port

iperf3 -s -D
Run as a background daemon

RUNNING A TEST

iperf3 -c *<host>*
Run a TCP test

iperf3 -c *<host>* **-p** *<port>*
Connect to another port

iperf3 -c *<host>* **-t** *<sec>*
Set duration (default 10 s)

iperf3 -c *<host>* **-O** *<sec>*
Skip the first seconds in stats

DIRECTION & STREAMS

iperf3 -c *<host>* **-R**
Reverse: server sends to client

DIRECTION & STREAMS (cont.)

iperf3 -c *<host>* **--bidir**
Send and receive at the same time

iperf3 -c *<host>* **-P** *<n>*
Run n parallel streams

UDP & BITRATE

iperf3 -c *<host>* **-u**
Run a UDP test (1 Mbit/s default)

iperf3 -c *<host>* **-u -b** *<rate>*
UDP at a target rate, e.g. 100M

iperf3 -c *<host>* **-b** *<rate>*
Cap a TCP test's rate

iperf3 -c *<host>* **-u -R**
UDP loss and jitter, download

TUNING

iperf3 -c *<host>* **-w** *<size>*
Set socket buffer or window

OUTPUT

iperf3 -c *<host>* **-J**
Output as JSON

iperf3 -c *<host>* **-i** *<sec>*
Report interval (0 turns it off)

iperf3 -c *<host>* **-f** *<unit>*
Units: k, m, g, t (bits) or K, M, G, T (bytes)

iperf3 -c *<host>* **--get-server-output**
Also print the server's view

READING RESULTS

Output columns

Column	Meaning
`Transfer`	Data moved in the interval
`Bitrate`	Throughput in that interval
`Retr`	TCP retransmits (sender)
`Cwnd`	Congestion window (sender)
`Jitter`	UDP delay variation
`Lost/Total`	UDP datagrams lost / sent