kubeadm Bootstrap Kubernetes

START HERE

`kubeadm` **`init`**
Create a control plane

`kubeadm` **`upgrade apply v`***`<version>`*
Upgrade first control plane

`kubeadm` **`init --pod-network-cidr=`***`<cidr>`*
Init, sized for a CNI

`kubeadm` **`reset`**
Undo init or join

`kubeadm` **`join`** *`<host>`***`:6443 --token`** *`<token>`*
Add a node

`kubeadm` **`token create --print-join-command`**
Get a fresh join command

`kubeadm` **`certs check-expiration`**
When do certs expire?

`kubeadm` **`upgrade plan`**
What can I upgrade to?

Install runtime, kubelet, kubeadm → `kubeadm init` → **Control plane** static pods, admin.conf → `apply a CNI` → **Network** nodes become Ready → `kubeadm join` → **Workers** kubelet joins

CONCEPTS

kubeadm only bootstraps: it needs a container runtime and kubelet already installed, and you install a CNI plugin yourself afterwards.

Run kubeadm as root. Swap must be off and the node needs a unique hostname and reachable port 6443.

Upgrade one minor version at a time; never skip a minor.

BOOTSTRAP A CLUSTER

`kubeadm` **`init`**
Initialise a control-plane node

`kubeadm` **`init --pod-network-cidr=`***`<cidr>`*
Reserve the pod IP range for a CNI

`kubeadm` **`init --apiserver-advertise-address=`***`<ip>`*
Choose the API server IP

`kubeadm` **`init --control-plane-endpoint=`***`<dns>`***`:6443`**
Stable endpoint for HA control plane

`kubeadm` **`init --upload-certs`**
Share certs for more control planes

BOOTSTRAP A CLUSTER (cont.)

`kubeadm` **`init --config`** *`<file>`*
Init from a config file

`kubeadm` **`init --dry-run`**
Show what init would do

`kubeadm` **`init --kubernetes-version`** *`<version>`*
Pin the control-plane version

`kubeadm` **`init --cri-socket`** *`<socket>`*
Pick the container runtime socket

`kubeadm` **`init --service-cidr`** *`<cidr>`*
Change the Service IP range

`kubeadm` **`init --apiserver-cert-extra-sans`** *`<name>`*
Extra names on the API cert

`kubeadm` **`init --ignore-preflight-errors=`***`<check>`*
Downgrade a preflight error

`mkdir -p $HOME/.kube && sudo cp /etc/kubernetes/admin.conf $HOME/.kube/config`
Let kubectl talk to the cluster

JOIN NODES

`kubeadm` **`join`** *`<host>`***`:6443 --token`** *`<token>`* **`--discovery-token-ca-cert-hash sha256:`***`<hash>`*
Join a worker node

JOIN NODES (cont.)

`kubeadm` **`join`** *`<host>`***`:6443 ... --control-plane --certificate-key`** *`<key>`*
Join as a control-plane node

`kubeadm` **`join --config`** *`<file>`*
Join from a config file

`kubeadm` **`init phase upload-certs --upload-certs`**
Re-upload control-plane certs

TOKENS

`kubeadm` **`token create --print-join-command`**
New token plus full join command

`kubeadm` **`token list`**
List bootstrap tokens

`kubeadm` **`token create`**
Create a token (24h by default)

`kubeadm` **`token delete`** *`<token>`*
Revoke a token

`kubeadm` **`certs certificate-key`**
Generate a certificate key

`openssl x509 -pubkey -in /etc/kubernetes/pki/ca.crt | openssl rsa -pubin -outform der 2>/dev/null | openssl dgst -sha256 -hex | sed 's/^.* //'`
Compute the CA cert hash

CERTIFICATES

`kubeadm` **`certs check-expiration`**
Show expiry of all certs

`kubeadm` **`certs renew all`**
Renew every certificate

`kubeadm` **`certs renew`** *`<cert>`*
Renew one cert, e.g. apiserver

`kubeadm` **`kubeconfig user --client-name`** *`<user>`*
Make a kubeconfig for a user

After renewing, restart the control-plane static pods and copy the new admin.conf to your kubeconfig.

UPGRADE

`kubeadm` **`upgrade plan`**
Show available versions and checks

`kubeadm` **`upgrade apply v`***`<version>`*
Upgrade the first control plane

`kubeadm` **`upgrade node`**
Upgrade other nodes' local config

`kubectl drain` *`<node>`* **`--ignore-daemonsets`**
Evict pods before upgrading kubelet

`kubectl uncordon` *`<node>`*
Make the node schedulable again

UPGRADE (cont.)

`kubeadm` **`version -o short`**
Print the kubeadm version

CONFIG AND IMAGES

`kubeadm` **`config print init-defaults`**
Print the default init config

`kubeadm` **`config validate --config`** *`<file>`*
Check a config file

`kubeadm` **`config images list`**
List images kubeadm needs

`kubeadm` **`config images pull`**
Pre-pull the control-plane images

RESET

`kubeadm` **`reset`**
Revert init or join on this node

`kubeadm` **`reset --force`**
Reset without the prompt

`sudo rm -rf /etc/cni/net.d`
Remove leftover CNI config

`rm -rf $HOME/.kube`
Remove the stale kubeconfig

reset leaves CNI config, iptables rules and $HOME/.kube behind; clean them by hand before re-initialising.

RECIPES

Single-node cluster

```
sudo kubeadm init --pod-network-cidr=<cidr>
mkdir -p $HOME/.kube
sudo cp /etc/kubernetes/admin.conf $HOME/.kube/config
sudo chown $(id -u):$(id -g) $HOME/.kube/config
# install a CNI plugin, then
let pods run on the control plane
kubectl taint nodes --all node-role.kubernetes.io/control-plane-
```

Add a worker later

```
# on the control plane
kubeadm token create --print-join-command
# on the new node, as root
kubeadm join <host>:6443 --token <token> \
  --discovery-token-ca-cert-hash sha256:<hash>
```

Upgrade a control plane node

```
# upgrade the kubeadm package first, then
sudo kubeadm upgrade plan
sudo kubeadm upgrade apply v<version>
kubectl drain <node> --ignore-daemonsets
# upgrade kubelet and kubectl packages
sudo systemctl daemon-reload && sudo systemctl restart kubelet
kubectl uncordon <node>
```