mdadm Linux software RAID

Disks / partitions components `--create` → **/dev/md0** md array `mkfs` → **Filesystem** ext4, xfs, LVM… `mount` → **In use** watch /proc/mdstat

CONCEPTS

RAID is not a backup: it survives a disk failure, not deletion, corruption or a dead controller.

Create, grow and add start a background resync; the array is usable meanwhile but slower and not yet redundant.

Most commands need root and many write superblocks: double-check device names with lsblk first.

INSPECT

cat /proc/mdstat
Show arrays, members and sync progress

mdadm --detail *<md>*
Array state, level, members, UUID

mdadm --examine *<dev>*
Read the RAID superblock of a member

mdadm --query *<dev>*
Is this device an array or a member?

mdadm --detail --scan
One-line summary per active array

INSPECT (cont.)

mdadm --examine --scan
Find arrays on member superblocks

watch cat /proc/mdstat
Follow sync progress live

CREATE

mdadm --create *<md>* **--level=1 --raid-devices=2** *<dev1> <dev2>*
Mirror (RAID1) of two devices

mdadm --create *<md>* **--level=5 --raid-devices=3** *<dev1> <dev2> <dev3>*
RAID5: striping with parity

mdadm --create *<md>* **--level=6 --raid-devices=4** *<devs>*
RAID6: survives two failures

mdadm --create *<md>* **--level=0 --raid-devices=2** *<dev1> <dev2>*
RAID0: striping, no redundancy

mdadm --create *<md>* **--level=10 --raid-devices=4** *<devs>*
RAID10: mirrored stripes

mdadm --create ... --spare-devices=1 *<devs>*
Include a hot spare

CREATE (cont.)

mdadm --create ... --bitmap=internal
Write-intent bitmap, faster resync

Prefer partitions of type Linux RAID, or whole disks, of equal size; the smallest member sets the size.

FAIL, REPLACE, REPAIR

mdadm *<md>* **--fail** *<dev>*
Mark a member as faulty

mdadm *<md>* **--remove** *<dev>*
Remove a failed member

mdadm *<md>* **--add** *<dev>*
Add a disk; rebuild starts

mdadm *<md>* **--re-add** *<dev>*
Re-add a recently removed member

mdadm *<md>* **--replace** *<dev>* **--with** *<spare>*
Swap a disk while it is still healthy

mdadm *<md>* **--fail detached --remove detached**
Drop members whose device vanished

FAIL, REPLACE, REPAIR (cont.)

mdadm --zero-superblock *<dev>*
Erase RAID metadata from a disk

echo check > /sys/block/*<md>***/md/sync_action**
Scrub the array for mismatches

After a disk swap, copy the partition layout first (sfdisk -d | sfdisk), then --add the partition.

ASSEMBLE AND STOP

mdadm --assemble --scan
Assemble arrays from config or superblocks

mdadm --assemble *<md> <dev1> <dev2>*
Assemble one array from given members

mdadm --stop *<md>*
Deactivate an array (unmount first)

mdadm --stop --scan
Stop every array not in use

mdadm --assemble --run *<md> <devs>*
Start even with missing members

GROW AND RESHAPE

mdadm --grow *<md>* **--raid-devices=***<n>*
Change the number of active members

mdadm --grow *<md>* **--size=max**
Use all space after bigger members

mdadm --grow *<md>* **--bitmap=internal**
Add a write-intent bitmap

After growing, extend the filesystem (resize2fs, xfs_growfs) or the LVM layer on top.

CONFIG AND MONITORING

mdadm --detail --scan >> /etc/mdadm/mdadm.conf
Persist array definitions

mdadm --monitor --scan --daemonise
Run the monitor in the background

systemctl status mdmonitor
Check the monitor service

update-initramfs -u
Refresh initramfs (Debian/Ubuntu)