Nomad Workload orchestrator

CONCEPTS

> You submit a job; Nomad evaluates it and places allocations on client nodes. Status commands walk that chain.

Job your spec file
↓ evaluation
Eval scheduler run
↓ places
Allocation group on a node
↓ runs
Task container, process
↓ logs, exec

> job plan exits 0 for no change, 1 when allocations would change, 255 on error. Handy in CI.

> Job, alloc and node IDs can be shortened to a unique prefix.

CONNECT

export NOMAD_ADDR=<*url*>
Set the server address

export NOMAD_TOKEN=<*secret-id*>
Authenticate with an ACL token

export NOMAD_NAMESPACE=<*ns*>
Work in a namespace

nomad server members
List servers and leader

nomad version
Print the CLI version

RUN JOBS

nomad job init
Write example.nomad.hcl

nomad job validate <*file*>
Check a job file offline

nomad job plan <*file*>
Dry run with a diff

nomad job run <*file*>
Submit or update a job

nomad job run -detach <*file*>
Submit without monitoring

nomad job run -check-index <*n*> <*file*>
Submit only if unchanged since plan

RUN JOBS (cont.)

nomad job run -var <*key*>=<*value*> <*file*>
Set a job variable

INSPECT JOBS

nomad status
List all jobs

nomad job status <*job*>
Summary, allocations, deployment

nomad job inspect <*job*>
Show the stored job as JSON

nomad job history <*job*>
List versions of a job

nomad job allocs <*job*>
List allocations of a job

CHANGE AND STOP

nomad job stop <*job*>
Stop a job

nomad job stop -purge <*job*>
Stop and remove from the state

nomad job scale <*job*> <*group*> <*count*>
Set a task group count

nomad job revert <*job*> <*version*>
Roll back to an older version

nomad job restart <*job*>
Restart allocations in place

ALLOCATIONS

nomad alloc status <*alloc*>
Task states and events

nomad alloc logs <*alloc*> <*task*>
Print task stdout

nomad alloc logs -f <*alloc*> <*task*>
Follow logs

nomad alloc logs -job <*job*>
Logs of a random alloc of the job

nomad alloc exec <*alloc*> <*cmd*>
Run a command in a task

nomad alloc fs <*alloc*> [<*path*>]
Browse the allocation directory

nomad alloc restart <*alloc*>
Restart a task in place

NODES

nomad node status
List client nodes

nomad node status <*node*>
Resources and allocations of a node

nomad node drain -enable <*node*>
Migrate allocations away

nomad node drain -disable <*node*>
Cancel a drain

nomad node eligibility -disable <*node*>
Stop new placements

nomad node eligibility -enable <*node*>
Allow placements again

EVALS AND DEPLOYMENTS

nomad eval status <*eval*>
Why a placement failed

VARIABLES AND NAMESPACES

nomad var put <*path*> <*key*>=<*value*>
Write a variable

nomad var get <*path*>
Read a variable

RECIPES

Plan, then apply exactly that plan

```
nomad job plan web.nomad.hcl
# copy the Job Modify Index from the output
nomad job run -check-index <n> web.nomad.hcl
```

Drain a node for maintenance

```
nomad node drain -enable -yes <node>
nomad node status <node>
# ...maintenance...
nomad node drain -disable <node>
nomad node eligibility -enable <node>
```

Debug a failing task

```
nomad job status <job>
nomad alloc status <alloc>
nomad alloc logs -stderr <alloc> <task>
nomad alloc exec -task <task> <alloc> /bin/sh
```