virsh Manage libvirt VMs

CONCEPTS

As a normal user virsh talks to qemu:///session; system VMs live under qemu:///system, so add -c qemu:///system (or set LIBVIRT_DEFAULT_URI).

Connection -c qemu:///system
- **Domain (VM)** disks, NICs, CPU, RAM
  - **Network, pool, volume** shared host resources

destroy only stops a VM like a power cut; the definition stays. undefine removes the definition.

Changes to a running VM need --live, --config (next boot) or --persistent (both); without them behaviour depends on VM state.

CONNECT

virsh -c qemu:///system *<command>*
Run against the system hypervisor

virsh -c qemu:///session *<command>*
Run against your user session

virsh -c qemu+ssh://*<user>*@*<host>*/system list --all**
Manage a remote host over SSH

virsh
Interactive shell

virsh -r list
Read-only connection

virsh uri
Show the connection URI in use

LIFECYCLE

virsh list
Running VMs

virsh list --all
Running and stopped VMs

virsh start *<vm>*
Start a defined VM

virsh shutdown *<vm>*
Graceful ACPI shutdown

virsh reboot *<vm>*
Reboot gracefully

LIFECYCLE (cont.)

virsh destroy *<vm>*
Force off immediately

virsh suspend *<vm>*
Pause the VM in memory

virsh resume *<vm>*
Continue a paused VM

virsh start --console *<vm>*
Start and attach to console

virsh autostart *<vm>*
Start with the host

DEFINE & INSPECT

virsh dumpxml *<vm>*
Print the VM's XML

virsh edit *<vm>*
Edit the XML in $EDITOR

virsh define *<file.xml>*
Create a VM from XML

virsh undefine *<vm>*
Remove the definition

virsh dominfo *<vm>*
CPU, memory, state summary

CONSOLE & NETWORK ACCESS

virsh console *<vm>*
Serial console

virsh domifaddr *<vm>*
IP addresses of the VM

virsh domiflist *<vm>*
NICs with MAC and network

RESOURCES

virsh setmem *<vm>* *<size>*
Change memory of a running VM

virsh setvcpus *<vm>* *<n>* **--config**
Set vCPU count for next boot

DISKS & DEVICES

virsh domblklist *<vm>*
Disks and image paths

virsh attach-disk *<vm>* *<path>* *<target>* **--persistent**
Hot-add a disk

virsh detach-disk *<vm>* *<target>* **--persistent**
Remove a disk

SNAPSHOTS

virsh snapshot-create-as *<vm>* *<name>*
Create a snapshot

virsh snapshot-list *<vm>*
List snapshots

virsh snapshot-revert *<vm>* *<name>*
Roll back to a snapshot

virsh snapshot-delete *<vm>* *<name>*
Delete a snapshot

NETWORKS

virsh net-list --all
List virtual networks

virsh net-start *<net>*
Start a network

virsh net-autostart *<net>*
Start network at boot

virsh net-dhcp-leases *<net>*
Leases handed out

STORAGE

virsh pool-list --all
List storage pools

virsh pool-info *<pool>*
Capacity and state

virsh vol-list *<pool>*
Volumes in a pool

virsh vol-create-as *<pool>* *<name>* **20G --format qcow2**
Create a disk image

RECIPES

Find a VM's IP and log in

```
virsh -c qemu:///system domifaddr <vm>
ssh <user>@<ip>
```

Clean snapshot before an upgrade

```
virsh shutdown <vm>
virsh snapshot-create-as <vm> pre-upgrade
virsh start <vm>
# if it goes wrong:
virsh snapshot-revert <vm> pre-upgrade
```

Add a data disk

```
virsh vol-create-as default <vm>-data 10G --format qcow2
virsh attach-disk <vm> /var/lib/libvirt/images/<vm>-data \
  vdb --subdriver qcow2 --persistent
```