xdotool X11 input automation

CONCEPTS

xdotool fakes X11 input and drives windows. It needs an X server; under pure Wayland it only reaches XWayland apps.

search / getactivewindow fills the stack
↓ %1 %@
Window stack lives for one run
↓ cmd
windowactivate, key, ... act on %1 by default

Commands chain in one call and share the window stack: xdotool search --name Firefox windowactivate key ctrl+t.

Without --window, input goes through XTEST to the focused window. With --window it uses XSendEvent, which many apps ignore.

KEYBOARD

xdotool key *<keys>*
Press key combination(s)

xdotool key ctrl+shift+t
Combos are joined with +

xdotool key Return Tab
Several keys in a row

xdotool type "*<text>*"
Type a string

xdotool type --delay *<ms>* "*<text>*"
Slow down typing (default 12 ms)

xdotool key --clearmodifiers *<keys>*
Release held modifiers first

MOUSE

xdotool mousemove *<x>* *<y>*
Move pointer to absolute position

xdotool click *<button>*
Click: 1 left, 2 middle, 3 right

MOUSE (cont.)

xdotool click 4
Scroll up (5 scrolls down)

xdotool getmouselocation
Print x, y, screen, window

FIND WINDOWS

xdotool search --name *<regex>*
Windows whose title matches

xdotool search --class *<regex>*
Windows by WM_CLASS

xdotool search --onlyvisible *<regex>*
Only mapped windows

xdotool getactivewindow
Focused window id

xdotool selectwindow
Click a window to get its id

xdotool search --sync --class *<regex>*
Wait until a match appears

WINDOW CONTROL

xdotool windowactivate *<id>*
Switch desktop, raise, focus

xdotool windowactivate --sync *<id>*
Wait until it is active

xdotool windowmove *<x>* *<y>*
Move the window

xdotool windowsize *<w>* *<h>*
Resize (pixels or %)

DESKTOPS

xdotool get_desktop
Current desktop number

xdotool set_desktop *<n>*
Switch to desktop n (0-based)

SCRIPTING

xdotool sleep *<seconds>*
Pause inside a chain (fractions ok)