k3d k3s in Docker

CONCEPTS

Docker host your machine
Cluster network k3d-<name>
Nodes serverlb, server-N, agent-N

One Docker network per cluster

Every node is a Docker container named k3d-<cluster>-<role>-<n>. Host ports reach the cluster through the k3d-<cluster>-serverlb container, so map ports with @loadbalancer.

CLUSTERS

k3d cluster create *<name>*
Create a cluster

k3d cluster list
List clusters and node counts

k3d cluster delete *<name>*
Delete a cluster

k3d cluster delete --all
Delete every cluster

k3d cluster stop *<name>*
Stop the cluster containers

k3d cluster start *<name>*
Start a stopped cluster

k3d cluster create *<name>* **-s** *<n>* **-a** *<n>*
Set server and agent count

k3d cluster create *<name>* **-i** *<image>*
Pick the k3s version via image

PORTS AND NETWORKING

k3d cluster create -p "8080:80@loadbalancer"
Map host port to ingress

KUBECONFIG

k3d kubeconfig merge *<name>* **--kubeconfig-switch-context**
Merge and switch context

KUBECONFIG (cont.)

k3d kubeconfig get *<name>*
Print a cluster's kubeconfig

NODES

k3d node list
List all nodes

k3d node create *<name>* **-c** *<cluster>*
Add an agent to a cluster

k3d node delete *<node>*
Remove a node

IMAGES AND REGISTRIES

k3d image import *<image>* **-c** *<name>*
Copy a local image into nodes

k3d registry create *<name>* **--port** *<port>*
Create a local registry

k3d cluster create --registry-create *<name>*
Make a registry with the cluster

k3d cluster create --registry-use k3d-*<name>***:***<port>*
Use an existing registry

MOUNTS, ENV AND K3S ARGS

k3d cluster create -v *<host>***:***<node>***@***<filter>*
Mount a host path

k3d cluster create --k3s-arg "*<arg>***@server:*"**
Pass a flag to k3s

CONFIG FILE

k3d cluster create --config *<file>*
Create from a config file

MAINTENANCE

k3d version
Show k3d and k3s versions